

The lstautogobble Package

Martin Scharrer
martin@scharrer-online.de

CTAN: <http://www.ctan.org/pkg/lstautogobble>

VC: https://bitbucket.org/martin_scharrer/lstautogobble

Version v0.1 – 2012/05/03

Abstract

This add-on package to `listings` provides a boolean `autogobble` setting which will automatically set the `gobble` setting to indentation of the first line.

This package was created as response to the question “[How to automatically skip leading white spaces in listings?](#)” on [T_EX Stack Exchange](#).

1 Introduction

The `listings` package has a setting `gobble=<number>` which allows to remove a certain number of characters from the beginning of every line in the listing. This can be used to indent the listing in the source code without affecting the printed result. However, this forces the user to set a suitable value manually. An incorrect value will lead either to an indented listing or to missing leading characters.

A solution for this is to automatically detect the used indentation of the listing and that the `gobble` setting to this value. This functionality is provided by this package. For this it reads and scans the first listing line and reinserts it again afterwards.

2 Usage

After loading `lstautogobble` the following new `listings` setting is available:

```
autogobble=true|false
```

This boolean setting switches the `autogobble` feature on or off. If no value is used the default is ‘true’. The initial setting is ‘false’. One enabled the first line of any `lstlisting` is scanned and the amount of spaces or tabulators is used to set the `gobble` setting. If `gobble` is set manually it will not be overwritten and `autogobble=true` is ignored.

3 Examples / Tests

The following code is intended as examples and also for testing the package. Here the `autogobble` feature is globally enabled.

```
test
it
```

```
1 \begin{lstlisting}
2   test
3   it
4 \end{lstlisting}
```

Example 1: Only environment (with `autogobble` enabled globally).

```
test
it
```

```
1 \begin{lstlisting}[basicstyle=\ttfamily\scriptsize]
2   test
3   it
4 \end{lstlisting}
```

Example 2: With options (must be skipped and reinserted).

```
est
t
```

```
1 \begin{lstlisting}[gobble=7]
2   test
3   it
4 \end{lstlisting}
```

Example 3: Manual gobble option (override). Intentionally set to an incorrect value.

```
test
it
```

```
1 \begin{lstlisting}[autogobble=false]
2   test
3   it
4 \end{lstlisting}
```

Example 4: Locally turned-off `autogobble`.

```
test
it
```

```
1 \begin{lstlisting} some text at the first line
2   test
3   it
4 \end{lstlisting}
```

Example 5: With some material on the same line as `\begin` (dropped by listings. The warning message got preserved).

```
test
it
```

```
1 \begin{lstlisting}[] some text at the first line
2   test
3   it
4 \end{lstlisting}
```

Example 6: As before, but with optional argument.

```
test
it
```

```
test
it
```

```
test
it
```

```
test
it
```

```
test
it
```

```
1 \begin{lstlisting}
2   test
3   it
4 \end{lstlisting}
```

```
1 \begin{lstlisting}
2   test
3   it
4 \end{lstlisting}
```

```
1 \begin{lstlisting}
2 test
3 it
4 \end{lstlisting}
```

```
1 \begin{lstlisting}
2           test
3           it
4 \end{lstlisting}
```

```
1 \begin{lstlisting}
2           test
3           it
4 \end{lstlisting}
```

Example 7: Different indention levels.

```
#include <stdio.h>
int main(){
    printf("tex.stackexchange.com: the coolest community ever!\n");
}
```

```
1 \begin{lstlisting}[autogobble]
2   #include <stdio.h>
3   int main(){
4     printf("tex.stackexchange.com: the coolest community ever!\n/
5     ");
6 \end{lstlisting}
```

Example 8: Some real C Code.

4 Implementation

```
5 %<!COPYRIGHT>
6 \ProvidesPackage{lstautogobble}[%
7 %<!DATE>
8 %<!VERSION>
9 %<*DRIVER>
10     2099/01/01 develop
11 %</DRIVER>
12     Implements 'autogobble' option for 'listings']
13
14 % This is an add-on to the 'listings' package
15 \RequirePackage{listings}
16
17 % Counter for leading spaces
18 \newcount\lstag@spacecount
19
20 % Some macros for comparison:
21 \def\lstag@activespace{\lst@ProcessSpace}% /
22     Definition of an active space
23
24 \def\lstag@tabulator{\lst@ProcessTabulator}% /
25     Definition of an tabulator
26
27 \begingroup
28 \catcode'\^^M=\active%
29 \gdef\lstag@activenl{\^^M}% Active CR (ASCII 13) /
30     character which is used as line break
31 \endgroup
32
33 % Define 'autogobble' option as boolean (by default /
34     off)
35 \lst@Key{autogobble}{false}[t]{\lstKV@SetIf{#1}\
36     lst@ifautogobble}
37
38 % 'ungobble' option
39 \lst@Key{ungobble}{0}{\def\lst@ungobble{#1}}
40
41 % Insert required code at environment init
42 \lst@AddToHook{Init}{\lst@autogobble}
43
44 % Autogobble init macro.
45 % If the option is active and 'gobble' is not set, /
46     init vars and overwrite the process macro with own /
47     definition.
48 \def\lst@autogobble{%
49     \lst@ifautogobble
50         \ifnum\lst@gobble>0\else
51             \def\lst@gobble{\lstag@gobble}%
52         \fi
53     \fi
54 }
```

```

45         \def\lstag@gobble{0}%
46         \lstag@spacecount\z@
47         \def\lstag@spaceaccu{}%
48         \let\lstag@restofline\empty
49         \let\lstag@origlstenv@Process\
           lstenv@Process
50         \let\lstenv@Process\
           lstag@countleadingspaces
51     \fi
52 \fi
53 }
54
55 % Checks if the next following character (read as /
   argument) is a line break (as it is supposed to be/
   )
56 % Otherwise there is some text direct after the '\
   begin{<env>}[<options>]' which is dropped by '/
   listings'.
57 \def\lstag@countleadingspaces#1{%
58     \expandafter\ifx\lstag@activenl#1\relax
59         \expandafter\lstag@countleadingspaces@
60     \else
61         \def\lstag@restofline{Dummy replacement of /
           text after begin of listing to trigger /
           original warning message}%
62         \expandafter\lstag@countleadingspaces
63     \fi
64 }
65
66 % After the new line is found this macro counts the /
   spaces and tabulators
67 \def\lstag@countleadingspaces@#1{%
68     \ifx\lstag@activespace#1\relax
69         \advance\lstag@spacecount by \@ne
70         % Accumulate spaces (i.e. their definitions) /
           for later re-insertion:
71         \expandafter\def\expandafter\lstag@spaceaccu\
           \expandafter{\lstag@spaceaccu\
           lst@ProcessSpace}%
72         \let\next\lstag@countleadingspaces@
73     \else% Character wasn't a space
74     \ifx\lstag@tabulator#1\relax
75         \advance\lstag@spacecount by \lst@tabsize\
           relax
76         % Accumulate spaces (i.e. their definitions) /
           for later re-insertion:
77         \@tempcnta=\lst@tabsize\relax
78         \loop
79         \ifnum\@tempcnta>\z@
80             \expandafter\def\expandafter\

```

```

      lstag@spaceaccu\expandafter{\
      lstag@spaceaccu\lst@ProcessSpace}%
81     \advance\@tempcnta\m@ne
82     \repeat
83     \let\next\lstag@countleadingspaces@
84 \else% Character wasn't a tabulator either
85     % Set gobble option (indirect):
86     \xdef\lstag@gobble{\the\numexpr\
      lstag@spacecount-\lst@ungobble\relax}%
87     % Restore original definition of process /
      macro:
88     \global\let\lstenv@Process\
      lstag@origlstenv@Process
89     % Re-insert all collected material or /
      appropriate replacement material:
90     \edef\next{\noexpand\lstenv@Process\
      lstag@restofline\expandafter\noexpand\
      lstag@activenl\expandafter\nexpanded\
      expandafter{\lstag@spaceaccu}\noexpand#1}%
91 \fi\fi
92 \next
93 }

```